



Export


Getting Started with Detective

Customize and generate reports in multiple formats including PDF, XLS, XLSX, and HTML. You may also export to Relativity software.

Oxygen Forensic software enables the export of data from any section to many popular file formats, including PDF, XLSX, XML, HTML, and JSON Project VIC. A report can be created to include a single device, several devices, several sections, or even selected records. Reports are highly customizable to display the data required, for any type of case. Our XML reports can be integrated into many popular analytic software platforms with our built in XML export specification documentation. Export to Relativity software is also available.


The screenshot shows the 'Export' dialog box with the following details:

- Export selected sections:**
 - Sections (14):
 - Device Information
 - Calendar (524)
 - Apple Notes (31)
 - OS Artifacts (679)
 - Wireless Connections (245)
 - WebKit Data (225)
 - Key Evidence (18)
 - > Files (36451)
 - Contacts (327)
 - Search (812)
 - Timeline (46144)
 - Accounts and Passwords (912)
 - Calls (721)
 - Messages (7490)
 - Applications (26):
 - Amazon shopping (20)
 - Phonebook (209)
 - Health (32492)
 - Apple Maps (20)
 - Apple Messages (7487)
 - Safari Browser (3435)
 - Apple Wallet (77)
 - Event Log (476)
 - Voice Memos (14)
 - Instagram (111)
 - Fly Delta (60)
 - Facebook (14)
 - Facebook Messenger (1060)
 - Dropbox (1)
- Export folder:** C:\Users\Mahan\Desktop\
- File name:** Kiara Hill-Apple iPhone 7 Plus-06012020101816
- Export format:** PDF (selected)
 - PDF
 - XLSX - Table view 2010
 - HTML - Table view
 - XML export
 - JSON Project VIC
- Options:**
 - Export files from the selected sections
 - Export only records marked as key evidence
 - Export each section to separate file
- Buttons:** Save settings, Export, Cancel




General:

- Control which Sections and Applications
- Choose your report locations and file name.
- Choose the format (PDF, XLSX, HTML, XML, JSON)
- Options to Export files from Sections, Export only Key Evidence, and Export each section into its own report.




Common:

- Group files by type
- Control your XLSX and HTML options.
- Control the font settings
- Choose to password protect your PDF and/or XLSX reports and input your password.




Sections:

- General Sections:
 - Device Information
 - Accounts and Passwords
 - Apple Notes
 - Calendar
 - Files
 - Messages
 - Artifacts
 - Webkit Data
 - (ANY other section that has been parsed in your device)
- Analytics
 - Key Evidence
 - Search
 - Timeline
- Applications
 - (ALL APPLICATIONS PARSED In your device)




Files:

- Choose the file format options
 - Export to file
 - Save files to other files folder
 - Include known/system files
- Use the filter to choose which types of files to export.
 - Add a new filter
 - Delete Filters




Date Filters:

- Quickly and efficiently narrow your report by selecting a date filter.
- Choose multiple date ranges by adding new date filters.




Header and Footer:

- Control what your report looks like by altering the header and footer to include information such as device alias, dates, and/or Detective version.
- Add an agency or business logo to personalize your report.
- Save your template to use again.



Tags:


- Control which tags to export or export them all.
- Choose whether or not to export only the items you have marked with tags.
- The numbers listed next to each tag represents how many tags of each will be in your report.



Project VIC:





Control your parameters for Project VIC to include:

- Case Information
- Media
- Medial Files
- OData
- Exported Data



Templates:

Refer back to this page to access the templates you have created and saved.



Other Export Options and Functions:

This icon is in the Extraction Information section of the device. Here you can export the device into a report and/or to Relativity

This Export icon is located inside each section. The printer icon with selection boxes in its row represents which items you've chosen to be exported. By default, they are all selected.

These are the Sections options when you export on a CASE level.

Exporting on a DEVICE level will also have the Applications option where CASE level does not.

Oxygen Forensics
901 N. Pitt St, Suite 100
Alexandria, VA 22314
United States
+1 (877) 9-OXYGEN
+1 (877) 969-9436
+1 (703) 888-2327